

Parefeux sous OMV

The screenshot shows the OpenMediaVault web interface for firewall configuration. The 'Pare-feu' tab is active, displaying a list of rules for IPv4. The table below represents the data shown in the interface.

Direction	Action	Famille	Source	Port	Destina...	Port	Proto...	Options supplémentaires	Commentaire
INPUT	ACCEPT	IPv4	-	-	-	-	Tous	-i lo	Autoriser le trafic local
OUTPUT	ACCEPT	IPv4	-	-	-	-	Tous	-o lo	Autoriser le trafic local
INPUT	ACCEPT	IPv4	-	-	-	-	Tous	-m conntrack --ctstate ESTABLISHED,RELATED	Conserver les connexions déjà établies
INPUT	ACCEPT	IPv4	192.168.1.2	-	-	-	Tous		Accès total à partir d'un poste particulier
INPUT	ACCEPT	IPv4	192.168.1.0/24	-	-	-	ICMP		PING en local
INPUT	ACCEPT	IPv4	192.168.1.0/24	-	-	5000	TCP		Accès à OpenMediaVault
INPUT	ACCEPT	IPv4	-	-	-	22	TCP		Autoriser SSH
INPUT	ACCEPT	IPv4	-	-	-	80	TCP		Autoriser HTTP
INPUT	ACCEPT	IPv4	-	-	-	443	TCP		Autoriser HTTPS
INPUT	ACCEPT	IPv4	-	-	-	137	UDP		Samba : NetBIOS Name Service
INPUT	ACCEPT	IPv4	-	-	-	138	UDP		Samba : NetBIOS Datagram Service
INPUT	ACCEPT	IPv4	-	-	-	139	TCP		Samba : NetBIOS Session Service
INPUT	ACCEPT	IPv4	-	-	-	445	TCP		Samba : SMB/CIFS Service
INPUT	ACCEPT	IPv4	-	-	-	53	UDP		DNS
INPUT	ACCEPT	IPv4	-	-	-	53	TCP		DNS
INPUT	DROP	IPv4	-	-	-	-	Tous		Interdire tout ce qui n'est pas autorisé

From: <https://magenealogie.chanterie37.fr/www/fablab37110/> - **Castel'Lab le Fablab MJC de Château-Renault**

Permanent link: <https://magenealogie.chanterie37.fr/www/fablab37110/doku.php?id=start:raspberrypi:firewall&rev=1736575800>

Last update: **2025/01/11 07:10**

