


Parefeux sous OMV



The screenshot shows the OpenMediaVault web interface for firewall configuration. The 'Pare-feu' tab is active, displaying a list of rules for the IPv4 family. The table below represents the data shown in the interface.

Direction	Action	Famille	Source	Port	Destina...	Port	Proto...	Options supplémentaires	Commentaire
INPUT	ACCEPT	IPv4	-	-	-	-	Tous	-i lo	Autoriser le trafic local
OUTPUT	ACCEPT	IPv4	-	-	-	-	Tous	-o lo	Autoriser le trafic local
INPUT	ACCEPT	IPv4	-	-	-	-	Tous	-m conntrack --ctstate ESTABLISHED,RELATED	Conservier les connexions déjà établies
INPUT	ACCEPT	IPv4	192.168.1.2	-	-	-	Tous		Accès total à partir d'un poste particulier
INPUT	ACCEPT	IPv4	192.168.1.0/24	-	-	-	ICMP		PING en local
INPUT	ACCEPT	IPv4	192.168.1.0/24	-	-	5000	TCP		Accès à OpenMediaVault
INPUT	ACCEPT	IPv4	-	-	-	22	TCP		Autoriser SSH
INPUT	ACCEPT	IPv4	-	-	-	80	TCP		Autoriser HTTP
INPUT	ACCEPT	IPv4	-	-	-	443	TCP		Autoriser HTTPS
INPUT	ACCEPT	IPv4	-	-	-	137	UDP		Samba : NetBIOS Name Service
INPUT	ACCEPT	IPv4	-	-	-	138	UDP		Samba : NetBIOS Datagram Service
INPUT	ACCEPT	IPv4	-	-	-	139	TCP		Samba : NetBIOS Session Service
INPUT	ACCEPT	IPv4	-	-	-	445	TCP		Samba : SMB/CIFS Service
INPUT	ACCEPT	IPv4	-	-	-	53	UDP		DNS
INPUT	ACCEPT	IPv4	-	-	-	53	TCP		DNS
INPUT	DROP	IPv4	-	-	-	-	Tous		Interdire tout ce qui n'est pas autorisé

From: <https://magenealogie.chanterie37.fr/www/fablab37110/> - **Castel'Lab le Fablab MJC de Château-Renault**

Permanent link: <https://magenealogie.chanterie37.fr/www/fablab37110/doku.php?id=start:raspberrypi:firewall&rev=1736575800>

Last update: **2025/01/11 07:10**

